


# IPv4 Services

## NAT/PAT


# IP Addressing Services

## Scaling Networks With Network Address Translation (NAT)



# Scaling Networks With NAT

- All public Internet addresses must be registered with a **Regional Internet Registry (RIR)**.
- Organizations can lease public addresses from an ISP.
- Only the registered holder of a public Internet address can assign that address to a network device.



# Scaling Networks With NAT

- **Private Internet Addresses:**
  - These are reserved private Internet addresses drawn from three blocks.
  - These addresses are for **private, internal network use only**.
  - **RFC 1918** specifies that private addresses are **not to be routed over the Internet**.

Class	RFC 1918 Internal Address Range	CIDR Prefix
A	10.0.0.0 - 10.255.255.255	10.0.0.0/8
B	172.16.0.0 - 172.31.255.255	172.16.0.0/12
C	192.168.0.0 - 192.168.255.255	192.168.0.0/16

# Scaling Networks With NAT

- Private Internet Addresses:

- Two Issues:

- You cannot route private addresses over the Internet.
- There are not enough public addresses to allow organizations to provide one to every one of their hosts.


- Networks need a mechanism to translate private addresses to public addresses at the edge of their network that works in both directions.

- Solution – NAT.


Class	RFC 1918 Internal Address Range	CIDR Prefix
A	10.0.0.0 - 10.255.255.255	10.0.0.0/8
B	172.16.0.0 - 172.31.255.255	172.16.0.0/12
C	192.168.0.0 - 192.168.255.255	192.168.0.0/16

# What is NAT?

- The **DHCP server** assigns IP dynamic addresses to devices inside the network.
- **NAT-enabled routers** retain one or many valid Internet IP addresses **outside of the network**.
- When the client sends packets out of the network, NAT translates the internal IP address of the client to an external address.
- *To outside users, all traffic coming to and going from the network has the same IP address or is from the same pool of addresses.*




# What is NAT?




- A NAT enabled device typically operates at the border of a stub network.
- A stub network is a network that has a single connection to its neighbor network.

# What is NAT?



- When a host on the **inside** network wants to access a host on the **outside** network, the packet is sent to the border gateway router.
- The border gateway router performs the NAT process, translating the **inside private** address to an **outside public** address.


# What is NAT?



- The translation process uses an internal translation table.
- The contents of the table will vary depending on the type of network translation being implemented.
- We will be looking at the use of **static NAT**, **dynamic NAT** and **Port Address Translation (PAT)**.


# NAT Terminology

**Inside Network:**  
Usually an  
organization's LAN.




**Outside Network:**  
Usually the Internet but  
it can be any network.

# NAT Terminology



# NAT Terminology




# NAT Terminology

- **Inside Local Address:** ←
  - An **RFC 1918 address** assigned to a host on an inside network.
- **Inside Global Address:** ←
  - A valid **public address** that the host on the inside network is assigned as it **exits the router**.
- **Outside Global Address:** ←
  - A reachable IP address assigned to a host **on the Internet**.
- *Outside Local Address:*
  - A local address assigned to a host on an outside network.
  - *(Use beyond the scope of this course).*

# How Does NAT Work?

R2: I have a packet for the **outside network**.  
I must translate the IP address.


Send



# How Does NAT Work?

R2: I have a packet for the **inside network**.  
I must translate the IP address.

Receive




# Dynamic Mapping and Static Mapping

- **Dynamic Mapping:**

- Mapping of local addresses dynamically to a **pool of global addresses**.
- The hosts able to use NAT is **limited by the number** of addresses in the range.
- If you have allocated 6 public addresses for NAT, any 6 users can use NAT simultaneously.
  - The NAT device **dynamically assigns an address when a request is received**. When a session ends, the address is returned to the pool for another user.

NAT Table	
Inside Local	Inside Global
10.0.0.1	179.9.8.81
10.0.0.2	
10.0.0.3	
10.0.0.4	
10.0.0.5	
10.0.0.6	
10.0.0.7	
10.0.0.8	179.9.8.86



# Dynamic Mapping and Static Mapping

- **Static Mapping:**

- **One to one** mapping of local and global addresses.
- The hosts able to use NAT is **limited by the static assignment** in the table.

NAT Table	
Inside Local	Inside Global
10.0.0.1	179.9.8.81
10.0.0.2	179.9.8.82
10.0.0.3	179.9.8.83
10.0.0.4	179.9.8.84
10.0.0.5	179.9.8.85
10.0.0.6	179.9.8.86


- If you have allocated 6 public addresses for NAT, **only these 6 users can use NAT**.
  - No other network users will have access unless you allocate another global address and add it to the table.

# NAT Overload

- Port Address Translation (PAT):
  - Allows you to use a single Public IP address and assign it up to 65,536 inside hosts (4,000 is more realistic).
  - Modifies the TCP/UDP source port to track inside host addresses.
  - Tracks and translates:
    - Source IP Address.
    - Destination IP Address.
    - TCP/UDP Source Port Number.
  - These **uniquely identify** each connection for each stream of traffic.


# NAT Overload

- Port Address Translation (PAT):




# NAT Overload

- Port Address Translation (PAT):



# NAT Overload

- Port Address Translation (PAT): *NEXT AVAILABLE PORT*



# Benefits and Drawbacks

- NAT Benefits:
  - **Conserves** the legally registered addressing scheme.
  - Increases the **flexibility** of connections to the public network.
  - Provides **consistency** for internal network addressing schemes.
  - Provides network **security**.

# Benefits and Drawbacks


- NAT Drawbacks:
  - Performance is degraded.
  - End-to-end functionality is degraded.
  - End-to-end trace is lost.

# Configuring Static NAT

- Step 1:

- Specify static translation between an **inside local** and **inside global** address.


```
ip nat inside source static  
local-ip global-ip
```



# Configuring Static NAT

- Step 2:
  - Mark the router interfaces as an **inside interface** or an **outside interface**.

```
RA (config) #interface fa0/0  
RA (config-if) #ip address 10.1.1.1 255.255.255.0  
RA (config-if) #ip nat inside
```



```
ISP routing table:  
179.23.2.0 via 192.168.1.1
```

```
RA (config) #interface s0/0/0  
RA (config-if) #ip address 192.168.1.1 255.255.255.0  
RA (config-if) #ip nat outside
```

# Configuring Static NAT

- Summary:

10.1.1.2 will always translate to 179.23.2.2



```
RA (config) #ip nat inside source static 10.1.1.2 179.23.2.2
```

```
RA (config) #interface fa0/0
```

```
RA (config-if) #ip address 10.1.1.1 255.255.255.0
```

```
RA (config-if) #ip nat inside
```

```
RA (config) #interface s0/0/0
```

```
RA (config-if) #ip address 192.168.1.1 255.255.255.0
```

```
RA (config-if) #ip nat outside
```


# Configuring Dynamic NAT

1. Define a *named address pool* of outside addresses to be used for translation.
2. Define an *access list* to specify those inside addresses that are eligible for translation.
3. *Specify dynamic translation* between the inside addresses allowed by the access list and the pool of outside addresses.
4. *Mark the interfaces* as inside or outside.

# Configuring Dynamic NAT

- Step 1:
  - Define a *named address pool* of **outside addresses** to be used for translation.

```
ip nat pool name start-ip end-ip  
      (netmask netmask |  
       prefix-length prefix-length)
```



# Configuring Dynamic NAT

- Step 1:

- Define a *named address pool* of *outside addresses* to be used for translation.


```
ip nat pool NAT-POOL1 179.9.8.80 179.9.8.85
```

Range

```
netmask 255.255.255.0
```

Name


Mask



# Configuring Dynamic NAT

- Step 2:
  - Define an *access list* to specify those **inside addresses** that are eligible for translation.

```
ip access-list standard access-list-name  
    permit source [source wildcard]
```



# Configuring Dynamic NAT


- Step 2:

- Define an *access list* to specify those **inside addresses** that are eligible for translation.

```
ip access-list standard NAME
```

```
permit 10.1.0.0 0.0.255.255
```


Allows **ALL** inside network addresses to be translated.



# Configuring Dynamic NAT

- Step 2:
  - *Specify dynamic translation* between the **inside addresses** allowed by the **access list** and the **pool of outside addresses**.

```
ip nat inside source list access-list-name  
pool pool-name
```



# Configuring Dynamic NAT


- Step 3:

- *Specify dynamic translation* between the **inside addresses** allowed by the **access list** and the **pool of outside addresses**.

```
ip nat inside source list NAME pool NAT-POOL1
```

From Step 1


From Step 2



# Configuring Dynamic NAT

- Step 4:
  - *Mark the interfaces* as inside or outside.

```
RA (config) #interface fa0/0
RA (config-if) #ip address 10.1.1.1 255.255.255.0
RA (config-if) #ip nat inside
```




```
RA (config) #interface s0/0/0
RA (config-if) #ip address 192.168.1.1 255.255.255.0
RA (config-if) #ip nat outside
```

# Configuring Dynamic NAT

- Summary:

All inside hosts are eligible for NAT.



```
RA(config)#ip nat pool NAT-POOL1 179.9.8.80 179.9.8.85  
netmask 255.255.255.0
```

```
RA(config)#ip access-list standard NAT-LIST1  
RA(config-nacl)#permit 10.1.0.0 0.0.0.255
```

```
RA(config)#ip nat inside source list NAT-LIST1 pool NAT-POOL1
```

```
RA(config)#interface fa0/0  
RA(config-if)#ip address 10.1.1.1 255.255.255.0  
RA(config-if)#ip nat inside
```

```
RA(config)#interface s0/0/0  
RA(config-if)#ip address 192.168.1.1 255.255.255.0  
RA(config-if)#ip nat outside
```

# Configuring NAT Overload (PAT)


- There are **two possible ways** to configure overloading.
  - It depends on how the ISP allocates public IP addresses.
    - The ISP allocates **one** public IP address to the organization.
    - The ISP allocates **more than one** public IP address.
  - In either case, the configuration will include the **overload** keyword.
    - This keyword specifies to the router that **Port Address Translation (PAT)** is to be used.

# Configuring NAT Overload (PAT)

- The ISP allocates **one** public IP address to the organization.
  1. Assign the **IP address received from the ISP** as the IP address of the outside interface.
  2. Define a **standard access list** permitting those addresses to be translated.
  3. Establish **dynamic translation** specifying the **access list** and **the actual interface** instead of a pool of addresses and include the **overload** keyword.
  4. Identify the **inside and outside interfaces**.

# Configuring NAT Overload (PAT)

- The ISP allocates **one** public IP address to the organization.



```
R2(config)#ip access-list standard NAT-LIST1
R2(config-nacl)#permit 192.168.0.0 0.0.255.255
```

```
R2(config)#ip nat inside source list NAT-LIST1 interface s0/1/0 overload
```


```
R2 (config) #interface s0/0/0
R2 (config-if) ip address 10.1.1.2 255.255.255.252
R2 (config-if) ip nat inside
```

```
R2 (config) #interface s0/1/0
R2 (config-if) #ip address 209.165.200.225 255.255.255.252
R2 (config-if) #ip nat outside
```

Assigned by ISP

# Configuring NAT Overload (PAT)

- The ISP allocates **more than one** public IP address.



```
R2(config)#ip access-list standard NAT-LIST2  
R2(config-nacl)#permit 192.168.0.0 0.0.255.255
```

```
R2 (config) #ip nat pool NAT-POOL2 209.165.200.226 209.165.200.240
```

```
R2(config)#ip nat inside source list NAT-LIST2 pool NAT-POOL2 overload
```

```
R2 (config) #interface s0/0/0  
R2 (config-if) ip address 10.1.1.2 255.255.255.252  
R2 (config-if) ip nat inside
```

```
R2 (config) #interface s0/1/0  
R2 (config-if) #ip address 209.165.200.225 255.255.255.252  
R2 (config-if) #ip nat outside
```

# Verifying NAT and NAT Overload

- **show ip nat translations**

```
R2#show ip nat translations
Pro Inside global      Inside local      Outside local      Outside global
tcp 209.165.200.225:16642 192.168.10.10:16642 209.165.200.254:80 209.165.200.254:80
tcp 209.165.200.225:62452 192.168.11.10:62452 209.165.200.254:80 209.165.200.254:80

R2#show ip nat translations verbose
Pro Inside global      Inside local      Outside local      Outside global
tcp 209.165.200.225:16642 192.168.10.10:16642 209.165.200.254:80 209.165.200.254:80
  create 00:01:45, use 00:01:43 timeout:86400000, left 23:58:16, Map-Id(In): 1,
  flags:
extended, use_count: 0, entry-id: 4, lc_entries: 0
tcp 209.165.200.225:62452 192.168.11.10:62452 209.165.200.254:80 209.165.200.254:80
  create 00:00:37, use 00:00:35 timeout:86400000, left 23:59:24, Map-Id(In): 1,
  flags:
extended, use_count: 0, entry-id: 5, lc_entries: 0
R2#
```

# Verifying NAT and NAT Overload

- **show ip nat statistics**

```
R2#show ip nat translations
```

Pro	Inside global	Inside local	Outside local	Outside global
icmp	209.165.200.225:3	192.168.10.10:3	209.165.200.254:3	209.165.200.254:3
tcp	209.165.200.225:11679	192.168.10.10:11679	209.165.200.254:80	209.165.200.254:80
icmp	209.165.200.225:0	192.168.11.10:0	209.165.200.254:0	209.165.200.254:0
tcp	209.165.200.225:14462	192.168.11.10:14462	209.165.200.254:80	209.165.200.254:80

```
R2#show ip nat statistics
```

```
Total active translations: 3 (0 static, 3 dynamic; 3 extended)
```

```
Outside interfaces:
```

```
Serial0/1/0
```

```
Inside interfaces:
```

```
Serial0/0/0, Serial0/0/1
```

```
Hits: 173 Misses: 9
```

```
CEF Translated packets: 182, CEF Punted packets: 0
```

```
Expired translations: 6
```

```
Dynamic mappings:
```

```
-- Inside Source
```

```
[Id: 1] access-list 1 interface Serial0/1/0 refcount 3
```

```
Queued Packets: 0
```

```
R2#
```

# Verifying NAT and NAT Overload

- **clear ip nat translation**

Command	Description
<code>clear ip nat translation *</code>	Clears all dynamic address translation entries from the NAT translation table
<code>clear ip nat translation inside <i>global-ip local-ip</i> [ <b>outside</b> <i>local-ip global-ip</i> ]</code>	Clears a simple dynamic translation entry containing an inside translation or both inside and outside translation
<code>clear ip nat translation <i>protocol</i> inside <i>global-ip global-port local-ip local-port</i> [ <b>outside</b> <i>local-ip local-port global-ip global-port</i> ]</code>	Clears an extended dynamic translation entry

# Troubleshooting NAT and NAT Overload

- show ip nat translations
- clear ip nat translation
- debug ip nat


```
R2# debug ip nat
IP NAT debugging is on
R2#
*Oct  6 19:55:31.579: NAT*: s=192.168.10.10->209.165.200.225, d=209.165.200.254 [14434]
*Oct  6 19:55:31.595: NAT*: s=209.165.200.254, d=209.165.200.225->192.168.10.10 [6334]
*Oct  6 19:55:31.611: NAT*: s=192.168.10.10->209.165.200.225, d=209.165.200.254 [14435]
*Oct  6 19:55:31.619: NAT*: s=192.168.10.10->209.165.200.225, d=209.165.200.254 [14436]
*Oct  6 19:55:31.627: NAT*: s=192.168.10.10->209.165.200.225, d=209.165.200.254 [14437]
*Oct  6 19:55:31.631: NAT*: s=209.165.200.254, d=209.165.200.225->192.168.10.10 [6335]
*Oct  6 19:55:31.643: NAT*: s=209.165.200.254, d=209.165.200.225->192.168.10.10 [6336]
*Oct  6 19:55:31.647: NAT*: s=192.168.10.10->209.165.200.225, d=209.165.200.254 [14438]
*Oct  6 19:55:31.651: NAT*: s=209.165.200.254, d=209.165.200.225->192.168.10.10 [6337]
*Oct  6 19:55:31.655: NAT*: s=192.168.10.10->209.165.200.225, d=209.165.200.254 [14439]
*Oct  6 19:55:31.659: NAT*: s=209.165.200.254, d=209.165.200.225->192.168.10.10 [6338]

<Output omitted>
```


# Port Forwarding

- Port forwarding on your router allows you to enter a port number (or possibly a range or combination of numbers, depending on the router), and an IP address.
- All incoming connections with a matching port number will be forwarded to the internal computer with that address.
- A packet sent to the public IP address and port of a router can be forwarded to a private IP address and port in inside network.
- Port forwarding is helpful in situations where servers have private addresses, not reachable from the outside networks.


# Port Forwarding



# Port Forwarding



# SOHO Example



Wireless-N Broadband Router

Firmware Version: v0.93.3

**Applications & Gaming**

Setup Wireless Security Access Restrictions Applications & Gaming Administration Status

Single Port Forwarding Port Range Forwarding Port Range Triggering DMZ QoS

**Single Port Forwarding**

Application Name	External Port	Internal Port	Protocol	To IP Address	Enabled
Web Server	80	80	TCP	192.168.1. 254	<input checked="" type="checkbox"/>

Help...

# Configuring Port Forwarding with IOS

In IOS, Port forwarding is essentially a static NAT translation with a specified TCP or UDP port number.

